# Exclaimer Auto Responder 1.0 Release Notes

#### Release Number

The current Release Number for this product is: 1.0.60705.0

## **System Requirements**

Hardware	Minimum Requirements	Recommended Requirements
СРИ	x64 architecture-based computer. Intel Itanium family IA64 processor are not supported.	x64 architecture-based computer. Intel Itanium family IA64 processor are not supported.
Memory	2GB	4GB
Disk Space	350 MB	500MB
Screen Resolution	1024 x 768 pixels	1152 x 864 or higher
Software	Minimum Requirements	
Operating Systems	Windows Server 2003 R2 x64 (including all service pack levels).  Windows Server 2008 x64 (including all service pack levels).  Windows Server 2008 R2 x64 (including all service pack levels).  Windows Server 2012.  Windows Small Business Server 2008.  Windows Small Business Server 2011.	
Exchange Server	Microsoft Exchange Server 2007 SP1 Rollup 5 and above. Microsoft Exchange Server 2010 RTM and above. Microsoft Exchange Server 2013 RTM.	
Exchange Server Roles	Microsoft Exchange Hub Transport Server (2007 & 2010) Microsoft Exchange CAS and or Mailbox Server (2013 only)	
Microsoft .Net Framework	Microsoft .Net Framework 2.0.	

## Downloading

Please refer to the following link on the Exclaimer website: <a href="http://www.exclaimer.com/downloads/auto-responder/default.aspx">http://www.exclaimer.com/downloads/auto-responder/default.aspx</a>

# Installing

Download the 'Auto Responder 1.0' installation file 'setup.exe' and run on the Microsoft Exchange Hub Transport Server for Exchange 2007/2010 or CAS and or Mailbox Server for Exchange 2013. An MSI is available from support by contacting <a href="mailto:support@exclaimer.com">support@exclaimer.com</a>.

## Uninstalling

Uninstall can be achieved via the 'setup.exe' or MSI for the currently installed version of 'Auto Responder 1.0' or via 'Add/Remove Programs' in Windows Server 2003 or 'Programs and Features' in Windows Server 2008 & 2012.

The configuration files are located in the following folder and will not be removed as part of the uninstall process:

Operating System	Minimum Requirements
Windows Server 2003 R2 x64	\Documents and Settings\All Users\Application Data\Exclaimer Ltd\Auto Responder
Windows Server 2008 x64 Windows Server 2008 R2 x64	
Windows Server 2012	\ProgramData\Exclaimer Ltd\Auto Responder
Windows Small Business Server 2008	
Windows Small Business Server 2011	

The uninstall process will not lose any of your configuration or settings. However as a backup precaution you may wish to export your configuration.

#### **Export Steps**

- 1. Open the Exclaimer Console.
- 2. Select the 'Exclaimer' node.
- 3. Open the 'Action' menu.
- 4. Select 'Export Configuration...'
- 5. Select a location and filename for the export.
- 6. Press Save.

This will export all your settings including all your templates and licensing data.

#### **Upgrading**

Upgrading can be achieved by following the steps above to uninstall the current version and then install the new version. You may optionally stop the Microsoft Exchange Transport service once Exclaimer Auto Responder has been uninstalled. The installation of a new version of Exclaimer Auto Responder will start the Microsoft Exchange Transport service.

#### **Fixed Issues**

• Exclaimer Mail Disclaimers unable to disclaim messages generated by Exclaimer Auto Responder.