

# Exclaimer Signature Manager Exchange Edition Release Notes

## Version Number

The current version number for this product is: 2.0.4

## System Requirements

Hardware	Minimum Requirements	Recommended Requirements
CPU	x64 architecture-based computer. Intel Itanium family IA64 processor are not supported.	x64 architecture-based computer. Intel Itanium family IA64 processor are not supported.
Memory	2GB	4GB
Disk Space	350 MB	500MB
Screen Resolution	1024 x 768 pixels	1152 x 864 or higher
Software	Minimum Requirements	
Operating Systems	Windows Server 2003 R2 x64 (including all service pack levels). Windows Server 2008 x64 (including all service pack levels). Windows Server 2008 R2 x64 (including all service pack levels). Windows Server 2012. Windows Server 2012 R2. Windows Small Business Server 2008. Windows Small Business Server 2011.	
Exchange Server	Microsoft Exchange Server 2007 SP1 Rollup 5 and above. Microsoft Exchange Server 2010 RTM and above. Microsoft Exchange Server 2013 RTM and above.	
Exchange Server Roles	Microsoft Exchange Hub Transport Server (2007 & 2010) Microsoft Exchange Mailbox Server (2013 only)	
Microsoft .Net Framework	Microsoft .Net Framework 4.0 or 3.5.1	

## Downloading

Please refer to the following link on the Exclaimer website:

<http://www.exclaimer.com/signature-manager-exchange-edition/download>

## Installing

Download the 'Signature Manager Exchange Edition 2.0.4' installation file 'setup.exe' and run on the Microsoft Exchange Hub Transport Server and/or Microsoft Exchange Mailbox server (Exchange 2013 only). An MSI is available from support by contacting [support@exclaimer.com](mailto:support@exclaimer.com).

## Uninstalling

Uninstall can be achieved via the 'setup.exe' or MSI for the currently installed version of 'Signature Manager Exchange Edition' or via 'Add/Remove Programs' in Windows Server 2003 or 'Programs and Features' in Windows Server 2008 & 2012.

The configuration files are located in the following folder and will not be removed as part of the uninstall process:

Operating System	File Location
Windows Server 2003 R2 x64	\Documents and Settings\All Users\Application Data\Exclaimer Ltd\Mail Disclaimers
Windows Server 2008 x64 Windows Server 2008 R2 x64 Windows Server 2012 Windows Server 2012 R2 Windows Small Business Server 2008 Windows Small Business Server 2011	\ProgramData\Exclaimer Ltd\Mail Disclaimers

The uninstall process will not lose any of your configuration or settings. However as a backup precaution you may wish to export your configuration.

### Export Steps

1. Open the Exclaimer Console.
2. Select the 'Exclaimer' node.
3. Open the 'Action' menu.
4. Select 'Export Configuration...'
5. Select a location and filename for the export.
6. Press Save.

This will export all your settings including all your templates and licensing data.

### Upgrading

Upgrading can be achieved via the 'setup.exe' which will perform an in-place upgrade.

### Fixed Issues

- Excessive memory usage of EdgeTransport.
- Group enumeration not correctly detecting members of a group when the group and members are in different domains.
- When converting from Plain Text to HTML an incorrectly encoded UTF-16 Plain Text multipart is added with HTML content and can cause Far Eastern characters to appear in the message.