

# Exclaimer Signature Manager Exchange Edition 2.2.9 Release Notes

## Version Number

The current version number for this product is: 2.2.9

## System Requirements

Hardware	Minimum Requirements	Recommended Requirements
CPU	x64 architecture-based computer. Intel Itanium family IA64 processor are not supported	x64 architecture-based computer. Intel Itanium family IA64 processor are not supported
Memory	2GB	4GB
Disk Space	350 MB	500MB
Screen Resolution	1024 x 768 pixels	1152 x 864 or higher
Software	Minimum Requirements	
Operating Systems	Windows Server 2008 x64 (including all service pack levels) Windows Server 2008 R2 x64 (including all service pack levels) Windows Server 2012 Windows Server 2012 R2 Windows Server 2016 Windows Small Business Server 2008 Windows Small Business Server 2011	
Exchange Server	Microsoft Exchange Server 2010 RTM and above Microsoft Exchange Server 2013 RTM and above Microsoft Exchange Server 2016 RTM and above	
Exchange Server Roles	Microsoft Exchange Hub Transport Server (2010) Microsoft Exchange Mailbox Server (2013 & 2016)	
Microsoft .Net Framework	Microsoft .Net Framework 4.5.2 or above	

## Downloading

Please refer to the following link on the Exclaimer website:

<http://www.exclaimer.com/signature-manager-exchange-edition/download>.

## Installing

Download the '**Signature Manager Exchange Edition 2.2.9**' installation file 'setup.exe' and run on the Microsoft Exchange Hub Transport Server and/or Microsoft Exchange Mailbox server (Exchange 2013 & 2016). An MSI is available from support by contacting [support@exclaimer.com](mailto:support@exclaimer.com).

## Uninstalling

Uninstall can be achieved via the 'setup.exe' or MSI for the currently installed version of 'Signature Manager Exchange Edition' or via 'Programs and Features' in Windows Server in your operating systems.

The configuration files are located in **\ProgramData\Exclaimer Ltd\Mail Disclaimers** and these are not be removed as part of the uninstall process. The uninstall process will not lose any of your configuration or settings. However, as a backup precaution you may wish to export your configuration, as summarised below:

### Export Steps

1. Open the Exclaimer Console.
2. Select the 'Exclaimer' node.
3. Open the 'Action' menu.
4. Select 'Export Configuration...'
5. Select a location and filename for the export.
6. Press Save.

This will export all your settings including all your templates and licensing data.

### Upgrading

Upgrading can be achieved via the 'setup.exe' which will perform an in-place upgrade.

### Fixed Issues

- Adding content before opening HTML tag causes inescapable errors.
- The Exclaimer Signature Manager Exchange Edition Sent Items Update Service service terminated unexpectedly under heavy load.
- Chinese characters displayed incorrectly when a signature is applied to Rich Text and calendaring emails.

### Enhancements

- Maintenance release updating license information.
- Support for Microsoft .NET Framework 4.7.1 and .NET security updates.